



**British
Geological Survey**

NATURAL ENVIRONMENT RESEARCH COUNCIL

Installation and User Guide for the 2009A Open Source Release of BGS·SIGMAmobile

Spatial Geoscience Technologies Programme

Internal Report OR/09/037



BRITISH GEOLOGICAL SURVEY

SPATIAL GEOSCIENCE TECHNOLOGIES PROGRAMME

INTERNAL REPORT OR/09/037

Installation and User Guide for the 2009A Open Source Release of BGS·SIGMAmobile

C J Jordan, E J Bee, N A Smith, K I G Lawrie, A P Marchant, G
Wildman, J Bow, W Shelley & P Turner

The National Grid and other
Ordnance Survey data are used
with the permission of the
Controller of Her Majesty's
Stationery Office.
Ordnance Survey licence number
Licence No:100017897/2009.

Keywords

Report; digital, field, data,
capture, SIGMA.

Bibliographical reference

JORDAN C J, BEE E J, SMITH N A,
LAWRIE K I G, MARCHANT A P,
WILDMAN G, BOW J, SHELLEY W
& TURNER P. 2009. *Installation
and User Guide for the 2009A
Open Source Release of
BGS·SIGMAmobile. British
Geological Survey Internal
Report, OR/09/037. 64pp.*

Copyright in materials derived
from the British Geological
Survey's work is owned by the
Natural Environment Research
Council (NERC) and/or the
authority that commissioned the
work. You may not copy or adapt
this publication without first
obtaining permission.
Contact the BGS Intellectual
Property Rights Section, British
Geological Survey, Keyworth,
e-mail ipr@bgs.ac.uk You may
quote extracts of a reasonable
length without prior permission,
provided a full acknowledgement
is given of the source of the
extract.

© NERC 2009. All rights reserved

Keyworth, Nottingham British Geological Survey 2009

BRITISH GEOLOGICAL SURVEY

The full range of Survey publications is available from the BGS Sales Desks at Nottingham, Edinburgh and London; see contact details below or shop online at www.geologyshop.com

The London Information Office also maintains a reference collection of BGS publications including maps for consultation.

The Survey publishes an annual catalogue of its maps and other publications; this catalogue is available from any of the BGS Sales Desks.

The British Geological Survey carries out the geological survey of Great Britain and Northern Ireland (the latter as an agency service for the government of Northern Ireland), and of the surrounding continental shelf, as well as its basic research projects. It also undertakes programmes of British technical aid in geology in developing countries as arranged by the Department for International Development and other agencies.

The British Geological Survey is a component body of the Natural Environment Research Council.

British Geological Survey offices

BGS Central Enquiries Desk

Tel 0115 936 3143 Fax 0115 936 3276
email enquiries@bgs.ac.uk

Kingsley Dunham Centre, Keyworth, Nottingham NG12 5GG

Tel 0115 936 3241 Fax 0115 936 3488
email sales@bgs.ac.uk

Murchison House, West Mains Road, Edinburgh EH9 3LA

Tel 0131 667 1000 Fax 0131 668 2683
email scotsales@bgs.ac.uk

Natural History Museum, Cromwell Road, London SW7 5BD

Tel 020 7589 4090 Fax 020 7584 8270
Tel 020 7942 5344/45 email bgs_london@bgs.ac.uk

Columbus House, Greenmeadow Springs, Tongwynlais, Cardiff CF15 7NE

Tel 029 2052 1962 Fax 029 2052 1963

Maclean Building, Crowmarsh Gifford, Wallingford OX10 8BB

Tel 01491 838800 Fax 01491 692345

Geological Survey of Northern Ireland, Colby House, Stranmillis Court, Belfast BT9 5BF

Tel 028 9038 8462 Fax 028 9038 8461

www.bgs.ac.uk/gsni/

Parent Body

Natural Environment Research Council, Polaris House, North Star Avenue, Swindon SN2 1EU

Tel 01793 411500 Fax 01793 411501
www.nerc.ac.uk

Website www.bgs.ac.uk

Shop online at www.geologyshop.com

Foreword

The British Geological Survey began developing digital field mapping systems in 1989, however it was apparent that the commercially available hardware was not suitable at that time. In 2001 we revisited the topic under the System for Integrated Geoscience Mapping (SIGMA) programme. By 2003 BGS had developed a PDA (personal digital assistant) field system, which was superseded in 2005 when we began deploying a beta system on rugged Tablet PCs. The Tablet PC system, which we call BGS·SIGMA*mobile* is now used by BGS in mapping projects across the UK as well as overseas. It is now available in Open Source form via the BGS website, www.bgs.ac.uk under an agreement which stipulates that updates and modifications must be supplied to BGS in order to stimulate further developments.

It is envisaged that future releases will be made available from the BGS website incorporating new modules, modifications and upgrades.

This document has been written to guide users through the installation and use of BGS·SIGMA*mobile*.

We are happy to receive feedback emailed to sigma@bgs.ac.uk.

Acknowledgements

The authors would like to acknowledge the work of all the digital field data capture team since 2001, in particular Andrew Howard, Russell Lawley, John Laxton, Jon Ford and Bill Hatton. Furthermore, the BGS·SIGMA*mobile* system could not have been developed without the comments and feedback of our dedicated teams of field testers including Maxine Akhurst, Helen Burke, Tony Cooper, Andy Farrant, Andrew Finlayson, Martin Gillespie, Nick Golledge, Kathryn Goodenough, Mike Hall, Mat Hardenberg, Holger Kessler, Simon Price, Andreas Scheib and Chris Thomas.

Contents

Foreword	i
Acknowledgements	i
Contents	ii
Introduction	iii
1 Installation Instructions	4
1.1 System requirements	4
1.2 Installing tools	4
1.3 Microsoft Access 2003 SETUP	5
1.4 Setting up a project.....	5
2 Global Positioning System (GPS)	5
2.1 Projection Setup.....	5
2.2 ArcGIS GPS Setup Instructions	6
3 Using BGS·SIGMA<i>mobile</i>	11
3.1 Opening the BGS·SIGMA <i>mobile</i> GIS	11
3.2 Preparing BGS·SIGMA <i>mobile</i> for field use.....	12
3.3 The BGS·SIGMA <i>mobile</i> Graphical User Interface (GUI)	16
3.4 Using the digital field slip	23
3.5 Capturing structured data or detailed observations	32
3.6 Displaying structural information in BGS·SIGMA <i>mobile</i>	45
4 Using the BGS Integrated Tools	47
4.1 The BGS Compass Bearing Tool	47
4.2 The BGS Structure Contour Tool.....	48
5 Backing-up your data	53
6 Viewing sketches on the Desktop	53
7 Troubleshooting, bug reporting and feedback	54
8 Using BGS·SIGMA<i>mobile</i> outside the UK	55
Appendix Using the Basic Précis Tool	60

Introduction

This report serves as an installation and introductory user guide to BGS·SIGMA*mobile*, which is an application for digital geoscience field data collection developed within the British Geological Survey's SIGMA (System for Integrated Geoscience Mapping) programme within the Earth & Planetary Observation & Mapping Team. This document provides installation instructions, followed by a brief guide to using the application. In BGS we provide our field staff with a two-day training course, and while this guide does not replace that, it is hoped that these instructions will provide a basis for successful use of BGS·SIGMA*mobile* in your organisation.

BGS·SIGMA*mobile* is designed to run in the field on rugged Tablet PCs, but can also be used on a desktop PC. The system is a heavily customised ArcGIS 9.2 and MSAccess application. The user must have a licensed copy of ArcView ArcGIS and MSAccess 2003, BGS does not supply these.

The BGS uses the application on several models of Tablet PC including Itronix GoBooks, Xplore iX104s and GETAC V100's. This guide does not provide instructions to its use on specific hardware platforms.

BGS staff have used the system for mapping in locations including the UK, Ghana, Madagascar, Tajikistan, the Antarctic and the U.S.A. We use it as part of a workflow of other customised BGS-developed systems that enables us to:

1. automatically collate spatial information from our databases,
2. interpret new data from satellite imagery and digital photogrammetry,
3. take our baseline and interpreted data to the field,
4. populate corporate databases with our field data,
5. build 3D digital models and visualisations,
6. output our data in formats such as maps.

Further information on these steps is available from the BGS website at http://www.bgs.ac.uk/research/technologies_epo.html. Only the field system has been supplied in this Open Source agreement so you will need to build/define your own methods for integrating BGS·SIGMA*mobile* into your mapping workflow.

1 Installation Instructions

1.1 SYSTEM REQUIREMENTS

BGS·SIGMA*mobile* has been developed using ESRI's ArcGIS 9.2 software. It is built onto a relational database built in Access 2003. It is important that all users of BGS·SIGMA*mobile* use these versions of the software for this release of BGS·SIGMA*mobile* otherwise they may experience problems with some of the functionality.

BGS has developed several integrated tools that require additional installation. These are the BGS Bearing Tool, the BGS Fonts, the BGS GPS tool, the BGS Précis Tool, the BGS Sketch Tool and the BGS Structure Contour Tool.


Important Note: The Précis Tool must be installed for BGS·SIGMA*mobile* to run.

Ensure that your system has been set to UK language and regional settings, and therefore shows the 24hr clock. To check this, open the Control Panel and in Regional and Language Options check all settings.

1.2 INSTALLING TOOLS

The integrated tools that require installation are stored in the BGS·SIGMA*mobile* folder structure. The following instructions explain how to load each of the tools.

1. Install DotNet_Framework_2050727. From the DotNet_Framework_2050727 folder run dotnetfx.exe.
2. Install the BGS Sketch Tool. From the \BGS_SKETCH_TOOL\Install Files folder run the SketchTool.msi. If you are running the system on Windows XP also install WindowsXP-KB900722-v1-x86-ENU.exe.
3. Install the Bearing Tool. From the \BEARING_TOOL folder run the BearingToolInstall.msi. On the installation window select to allow everyone to access the tool.




4. Install the BGS Structure Contour Tool. From the \STRUCTURE_CONTOUR_TOOL\StructureContourTool_May2007\Install Files folder run the StructureContourToolDotNet2005Install.msi. On the installation form select to allow everyone to access the tool.
5. From the \PRECIS_TOOL folder run the setup.msi to install the BGS Précis Tool. On the installation form select to allow everyone to access the tool.

6. Install the BGS GPS Tool. From the \BGS_GPS_TOOL folder run the BGS_GPS_1.5.msi.
7. Load the BGS fonts. From the Control Panel select Fonts. From the File menu select Install New Font and browse to the \MOBILE_HELP_DOCUMENTATION\FontsV4 folder. Select All and click OK.

1.3 MICROSOFT ACCESS 2003 SETUP

This step will need to be repeated on the system if a different profile name is used.

For some of the BGS·SIGMA*mobile* macros to work, the Microsoft Access security level needs to be set to Low. Open Access 2003 from the programs menu and go to Tools > Macro > Security and toggle the Low button on.



1.4 SETTING UP A PROJECT

Data can either be added to a blank BGS·SIGMA*mobile*.mxd or, if a project GIS is already set up, layers can be dragged and dropped between the project GIS and the empty BGS·SIGMA*mobile* GIS. It is important that the BGS·SIGMA*mobile* layers GeoPoly, GeoLine, Map Face Note, National Grid QS and TestPointProjection remain in the project for the system to work.

Ensure that you start/run a BGS·SIGMA*mobile* instance by double-clicking on the MXD rather than opening a blank project and then opening BGS·SIGMA*mobile*.

2 Global Positioning System (GPS)

2.1 PROJECTION SETUP

For onshore field data collection in the UK, the British National Grid (BNG) projection, which has an OSGB 1936 datum, is used. The DFDC data frame in ArcMap should automatically have this as its projection. If it does not, then it needs to be set using the data frame properties dialogue box, Coordinate System tab.

GPS systems use the world geographic coordinate system (WGS 1984). Since the DFDC data frame in ArcMap and the GPS use different coordinate systems, it is essential that ArcMap knows how to read in the GPS signal and transform the latitude and longitude coordinates into OSGB coordinates that are accurately viewed within ArcMap. To do this, a file called TestPointProjection has been added to the project. This file has a WGS84 projection and forces ArcMap to store the transformation properties required to transform data from a WGS84 projection into BNG. This can be checked using the data frame properties dialogue box, Coordinate System tab. Click the

Transformations button to see the values ArcMap uses to convert between the coordinate systems. (N.B. - all the other layers in the data frame should have a BNG projection).


2.2 ARCGIS GPS SETUP INSTRUCTIONS


To use the GPS tools a system with a GPS receiver and software must be used.


2.2.1 Using the ArcGIS GPS tools


Note that there is an incompatibility issue with the ArcGIS GPS tools and some hardware systems that may cause an increase in computer crashes. If this is the case, the BGS GPS tool can be used instead (see 2.2.2 below).


2.2.1.1 CONNECTING TO THE GPS

1. Open BGS·SIGMA*mobile* from within Windows Explorer (or your Desktop shortcut) and use the GPS toolbar (or the GPS drop down on the menu bar) to set up the GPS connection as follows.
2. Click the GPS Connection Setup Option button  to open the GPS Connection Setup dialogue box. The datum on the receiver should be set to GCS_WGS_1984. Everything else should stay as default.




3. Click OK. Then click the Connect to GPS icon on the toolbar . If you get the warning message below, click OK. The error message is because the GPS uses a WGS84 coordinate system whereas the BGS·SIGMA*mobile* data frame is using BNG.




4. You can also see the GPS readings from the toolbar using the GPS position window button. 
5. You can now use the Display Options within GPS Tools to change how the GPS locator is displayed and whether you want a track log etc.


2.2.1.2 ARCGIS GPS TOOLBAR



1. **GPS Connection Setup** – enables the user to connect to the GPS through the correct COM port and using the correct baud rate.
2. **GPS Position Window** – displays useful information about the GPS connection and its current position. In advanced mode it is possible to see the satellite availability as well as time/date and magnetic variances, along with suggested accuracy measurements.



When there is no connection, the GPS window shows an estimated position in red as shown below.




3. **Open Connection** – Establishes a connection to the GPS.
4. **Close connection** – Closes the connection to the GPS.
5. **Pan to GPS position**
6. **Zoom to GPS position**
7. **Auto pan to GPS position** – turn on or off depending on whether you want the system to move the map view to the GPS position whilst you are walking.
8. **Add destination**– Sets the clicked point on the screen as the destination.
9. **Destination properties** – Sets the symbol and label for the destination flag and allows the user to show the bearing to the destination from their current location.
10. **Display options** – Sets how the GPS symbol is displayed.


2.2.2 Using the BGS GPS tools

2.2.2.1 BGS GPS TOOLBAR


1. If the BGS GPS Toolbar is not visible go to View > Toolbars and select it.




2. Click on the Main GPS Tool to open BGS GPS dialog box. Select Start GPS. The GPS tool will attempt to get a GPS fix.
3. To stop the GPS press the Start GPS button again.




4. Once the GPS has a fix you can pan or zoom to the GPS location using the Pan and Zoom buttons on the Main Toolbar. You can also set the BGS GPS to Automatically Pan by using the Main GPS Tool see the diagram below.



5. The GPS tool will scan all the communications ports that are available to the application. If COM2 is available this will automatically be selected
 - a. If you need to change the communication port go to GPS Configuration/COM Port/COM n (see below)



6. The first time the BGS GPS Tool is used in BGS·SIGMAmobile two shapefiles will be created – these files are created using the same spatial reference as the current data frame.
 - a. Current GPS location (Created at DocPath\GPS\GPS.shp)
 - b. GPS Log (Created at DocPath\GPS\GPS_Date_Time.shp)



2.2.2.2 MORE BGS GPS SETTINGS AND INFORMATION:


- The GPS shapefile has one point with the current GPS location marked within it. This location is a transformation from the GPS.
- The symbology of the GPS shapefile will be automatically set depending on the strength of the GPS signal. Red = No Signal, Yellow = Low Signal, Green = Good Signal.
- You can turn the GPS location on or off by clicking the layer button in the ArcGIS Table of Contents.
- The GPS log file will have a record for every interval, set using the auto pan interval.
- A column in the GPS log file has the date and time of the GPS point.

- You can turn the GPS log file on or off by clicking the layer button in the ArcGIS Layer Table of Contents.
- You can alter the critical battery level at which the GPS will turn off (see figure below). This is recommended to be at least 1% above the system's critical battery level. This setting will persist until the application is removed.



2.2.3 GPS in ArcMap - trouble shooting

If you think that the GPS position is being shown incorrectly in ArcMap, check the transformation settings in the data frame properties/coordinate system/transformations dialogue. It should appear as displayed in the image below. If this is not correct, then make sure that the TestPointProjection feature class and a feature class with BNG projection have been added to the data frame.



3 Using BGS·SIGMA*mobile*


The digital field data collection system has been developed using ArcGIS 9.2 and a personal geodatabase in Access 2003 which is viewable in Access 2000. Access 2003 offers greater capabilities than Access 2000, especially in terms of handwriting recognition support.

The system should be treated in much the same way as a paper map and its accompanying notebook; the only difference is that data are captured digitally. On a paper map, geologists make notes and observations by drawing lines, polygons, map face comments and points with labels to reference their geological notebook observations. The same is true in the digital system.

3.1 OPENING THE BGS·SIGMA*MOBILE* GIS


BGS·SIGMA*mobile* accesses code in the background whilst the system is being loaded. For this to work, the application needs to be opened either through a shortcut from the Desktop to the .mxd itself or by double-clicking the .mxd in the project folder in Windows Explorer. If the application is opened via ArcMap, you will come across an error in the code and will not be able to use the system. This is because ArcMap temporarily looks for the geodatabase in a bin folder rather than in its real location. For ease, and to reduce the risk of this error, you should create a shortcut on your system to the BGS·SIGMA*mobile*.mxd.

Once the BGS·SIGMA*mobile* GIS is opened a dialogue box will be displayed showing the project and user details which are currently in use. These are default settings, which are added to any data captured during fieldwork so that, in the future, it can always be determined who captured the data, when and for which project. The user can change the user name shown here to their own by selecting their name from a list of user names displayed in the dropdown list.



If a valid username does not exist in the dropdown list, or any of the project details are incorrect, the user will have to access and populate the user dictionary form through the project details button and make the appropriate changes here. You will also note that there is the option to change the starting locality number.


BGS·SIGMA*mobile* relies on particular layers to store field observations. These will appear in the Table of Contents (TOC) when you open the GIS. They should not be renamed or removed as their names are coded into the project. If they are renamed and you use one of the BGS·SIGMA*mobile* tools you will be alerted by a message box saying that the layer cannot be found. The layers which are specific to BGS·SIGMA*mobile* are:



These are all stored in the DFDC.mdb database.

3.2 PREPARING BGS·SIGMAMOBILE FOR FIELD USE

To begin a new project, copy the BGS·SIGMA*mobile* folder and subfolders from the zip file to the project workspace.



If a project GIS project file has already been created, then so long as it has been created in ArcGIS 9 or above, you can open both the project GIS and the BGS·SIGMA*mobile* GIS on your office PC and drag and drop the data layers from the Table of Contents (TOC) in the project GIS into the TOC of the BGS·SIGMA*mobile* GIS.

The BGS·SIGMA*mobile*.mxd can be renamed to reflect the project or the user. The DFDC database **MUST NOT** be renamed. Alternatively data layers can be added directly into BGS·SIGMA*mobile* using the add data button. If you do this, make sure you have created layer files (.lyr) first in order to save the legend symbology information.

Setting up project details

When you first open the BGS·SIGMA*mobile* GIS, the Project and User Details form will prompt you to check the default details. When creating the BGS·SIGMA*mobile* GIS for project use, these default details will be incorrect so you must amend these by opening the DFDC Project Details Menu and selecting Populate User Dictionary. The Populate Project Details Dictionary form will appear with four tabs. In BGS a table has been loaded with the names of all our staff, this will need to be compiled for your organisation. The user names are used to generate a UUID (unique user ID) for each map face note, line, polygon and observation so it is important that the details are added for your field staff / students.

Tab 1 – User Names

Populate Project Details Dictionary

Please use this form to add the project details to the database

User Names | Project Name and Code | Mapping Scale | Locality Number

Please select the name of each field staff member - click add after each name

Add

The list below shows your user pick list - select any names you wish to delete, then press delete.

MR TEST Delete

Close

This list refers to a list of names and usernames that are stored in the table called DIC_META_ORACLE_USER in the geodatabase. You can type in a name and it will appear in the list. You can then select it and add it to the list below. If the name you require does not appear, you can add it to the table in the Access database.

This is the list which appears in the project/user details form. The user can add or remove names from that list using this form. To delete a name, select it and click the delete button.

Tab 2 – Project Name and Code

Populate Project Details Dictionary

Please use this form to add the project details to the database

User Names | Project Name and Code | Mapping Scale | Locality Number

Please enter the project name

PLEASE ENTER PROJECT NAME

Please enter the project code

PROJCODE

ADD

Close

This form shows the project name and project code currently set in the database. You can replace these entries to ensure that the correct project code and name appear. Ensure both text boxes are entered before clicking the Add button.

Tab 3 – Mapping Scale

Populate Project Details Dictionary

Please use this form to add the project details to the database

User Names | Project Name and Code | Mapping Scale | Locality Number

Please enter the scale at which you are mapping

1:10000 Add

Close

The data manager should enter the scale at which the project is mapping at here, and then click add.

Tab 4 – Locality Number

Populate Project Details Dictionary

Please use this form to add the project details to the database

User Names | Project Name and Code | Mapping Scale | Locality Number

The next locality number that will be used is displayed below. If you wish to continue your numbering from a previous field season / mapping area please insert your next locality number and click Change

1 Change

NOTE: The locality number is stored in the DFDC.mdb therefore if you take a new blank database out in the field with you it is necessary to tell the system your next locality number that you wish to use.

Close

Change the locality number to that required for the start of your project.

Once these four sections have been populated with information, the user can check that the database is using the correct values by viewing Project and User Details form. All of these details are stored in the database table USER_DETAILS.

If any user names are missing from the list, you must close the BGS-SIGMAmobile.mxd, open the DFDC.mdb database and edit the table DIC_META_ORACLE_USER to include the name and user ID of the missing person.

Setting-up Project Dictionaries

Within the DFDC.mdb there are several dictionary tables. Some of these, such as BGS_DIC_ROCK_ALL are very extensive and would take up a lot of room in dropdown lists in

the field. To reduce the time spent searching through lists to find the right value, the dictionaries have been set up with a project control field because different projects map in different domains and will require different values. The data manager can go through each dictionary to check the project control box beside any dictionary value that they feel will be used within the mapping domain. This forces these checked dictionary values into alphabetical order at the top of a dropdown list on the system. The remaining values with no project control tick will be included, in alphabetical order, in the dropdown list, but below the checked values.

CODE	SOURCE_CODE	DESCRIPTION	TRANSLATION	STATU	USER ENTE	DATE ENTERED	USER UPDAT	DATE UPDATED	TRANSI ER	PROJECT CONTROL
+ FBSY	RN	FOID-BEARING-SYE	Foid-bearing-syenit	C	GRBA	24/02/2000 09:59:59	BGS	02/06/2004 21:25:00		<input checked="" type="checkbox"/>
+ FBTR	RN	FOID-BEARING-TRA	Foid-bearing-trachy	C	GRBA	24/02/2000 09:59:59	BGS	02/06/2004 21:25:00		<input type="checkbox"/>
+ FCMST	RN	MUDSTONE, FRIABI	Friable, Calcareous	C	AWEL	10/06/2002	BGS	02/06/2004 21:25:17		<input type="checkbox"/>
+ FDGB	RN	FOID-GABBRO	Foid-gabbro	C	GRBA	24/02/2000 09:59:59	BGS	02/06/2004 21:25:00		<input type="checkbox"/>
+ FDGBR	RN	FOID-GABBROIC-RO	Foid-gabbroic-rock	C	GRBA	24/02/2000 09:59:59	BGS	02/06/2004 21:25:06		<input type="checkbox"/>
+ FDI	RN	FOIDITE	Foidite	C	GRBA	24/02/2000 09:59:59	BGS	02/06/2004 21:25:00		<input type="checkbox"/>
+ FDIO	RN	FOID-DIORITE	Foid-diorite	C	AWEL	04/10/2001	BGS	02/06/2004 21:25:07		<input type="checkbox"/>
+ FDIR	RN	FOID-DIORITIC-ROCI	Foid-dioritic-rock	C	GRBA	24/02/2000 09:59:59	BGS	02/06/2004 21:25:00		<input type="checkbox"/>
+ FDIT	RN	FOIDITE (TAS)	Foidite (tas)	C	GRBA	24/02/2000 09:59:59	BGS	02/06/2004 21:25:00		<input type="checkbox"/>
+ FDO	RN	FOIDLITE	Foidlite	C	GRBA	24/02/2000 09:59:59	BGS	02/06/2004 21:25:00		<input type="checkbox"/>
+ FDOOR	RN	FOIDLITIC-ROCK	Foidlitic-rock	C	GRBA	24/02/2000 09:59:59	BGS	02/06/2004 21:25:06		<input type="checkbox"/>
+ FDSY	RN	FOID-SYENITE	Foid-syenite	C	GRBA	24/02/2000 09:59:59	BGS	02/06/2004 21:25:00		<input type="checkbox"/>
+ FDSYR	RN	FOID-SYENITIC-ROCI	Foid-syenitic-rock	C	GRBA	24/02/2000 09:59:59	BGS	02/06/2004 21:25:00		<input type="checkbox"/>
+ FEBST	RN	IRON-BOUNDSTONE	Iron-boundstone	C	GRBA	24/02/2000 09:59:59	BGS	02/06/2004 21:25:00		<input type="checkbox"/>
+ FECRTE	RN	FERRICRETE (IRON)	Ferricrete (iron Lat	C	GRBA	24/02/2000 09:59:59	BGS	02/06/2004 21:25:00		<input type="checkbox"/>
+ FEFBT	RN	FERROAN-CARBON	Ferroan-carbonatite	C	AWEL	10/06/2002	BGS	02/06/2004 21:25:17		<input type="checkbox"/>
+ FEGST	RN	IRON-GRAINSTONE	Iron-grainstone	C	GRBA	24/02/2000 09:59:59	BGS	02/06/2004 21:25:00		<input type="checkbox"/>
+ FEGV	RN	IRON-GRAVEL	Iron-gravel	C	GRBA	24/02/2000 09:59:59	BGS	02/06/2004 21:25:00		<input type="checkbox"/>
+ FELAB	RN	FELSITE, ALBITE	Albite Felsite	C	AWEL	01/09/2003 17:09:32	BGS	02/06/2004 21:25:20		<input checked="" type="checkbox"/>
+ FELAF	RN	FELSITE, APPINITIC	Appinitic Felsite	C	AWEL	30/06/2003 12:23:04	BGS	02/06/2004 21:25:19		<input type="checkbox"/>
+ FELAD	RN	FEL SITE, APPINITIC	Appinitic Felsite	C	AWEL	30/06/2003 12:23:04	BGS	02/06/2004 21:25:19		<input type="checkbox"/>


Sand and Gravel	On
Silt	On
Xenolithic Granite	On
Agate	Off
Agglomerate and Tuffite	Off
Albitised Felsite	Off
Alkali Basalt	Off
Alkali Granite	Off

Check values here if you want them to appear at the top of a dropdown list.

This means that all dictionary values will be available in the field, but only some will be listed at the top of the dropdown list

To edit the dictionaries you will need at least one field observation point added to the project; if necessary place a dummy field observation point on the map. When the database form opens go to the Housekeeping Tab and select View Manipulate Dictionaries. In the Dictionary Browser select the down arrow and choose the Dictionary you wish to change. You can also double-click on the DFDC.mdb in Windows Explorer, select a field observation point, and continue with the steps listed above.


3.3 THE BGS·SIGMAMOBILE GRAPHICAL USER INTERFACE (GUI)



The layout of the BGS·SIGMAmobile application is shown above.

3.3.1 BGS DFDC Tools Toolbar

This toolbar uses a subset of useful tools that appear on the default ArcGIS tools toolbar as well as customised DFDC tools developed in BGS. Each tool is outlined below but their best practice use is described in more detail later in this document.



1. ***Zoom in***
2. ***Zoom out***
3. ***Fixed zoom in*** - Zooms in to the centre of the map in steps.
4. ***Fixed zoom out*** - Zooms out of the centre of the map in steps.
5. ***Measure*** - Allows the user to measure a distance on the map.
6. ***Pan*** - Lets the user move the map centre.
7. ***Full Extent*** - Zooms to the full extent of all the data.
8. ***Go back to previous extent***
9. ***Go to next extent***
10. ***Identify*** – displays the attributes of a feature.
11. ***Zoom to selected features***
12. ***Select features*** - Selects map features that are set as selectable.
13. ***Clear selected features*** - (unselect the selected features).
14. ***Delete selected geofeatures and graphics*** - deletes those selected GeoPoly, GeoLine, Map Face Note, Field Observation Point or Graphic features.

15. **Select graphic elements** - this tool will select graphic elements in the map layout, but not features saved in the DFDC.
16. **Finish Sketch** - If you are creating a GeoLine or GeoPoly feature and find it difficult to double tap on the tablet to finish drawing, click this button instead and it will finish drawing for you.
17. **Toggle table of contents** - Toggle this on or off to view the TOC window or not.
18. **Map scale** - This combo box shows the current map scale. A new scale can be entered here and the map will zoom to the selected scale.

3.3.2 BGS DFDC Toolbar




1 2 3 4 5 6 7 8 9 10 11 12 13 14 15 16 17

1. **Add Map Face Note** - This tool enables the user to enter a map face note to the digital field slip.
2. **Edit Map Face Note** - This tool enables the user to edit the content of an existing map face note.
3. **Move Map Face Note Tool** - This tool allows the user to move the position of a map face note.
4. **Copy map face note** - This tool allows the user to copy a selected map face note to save time re-writing it.
5. **Add Notebook observation point** - This button allows the user to add a point to the map face. Once the point is added the notebook application opens.
6. **Edit Notebook observation point** - This button allows the user to edit an existing notebook point on the map face. Once the point is selected the notebook application opens.
7. **Précis tool** - Use this tool to identify a field observation point and view all the data entered at that point in a précis list within ArcMap. This tool is also available within the DFDC database.
8. **Draw GeoPoly** - This tool is used to draw a polygon on the field slip. Users select the colour and the shading of the polygon by changing the selections available in the form activated by button 11. The style in use is written on the button. The project leader must decide what combination of fill style and colour correspond to each type of feature being mapped. This will vary depending upon mapping domain and as such project specific.
9. **Draw GeoLine** - The user can use this tool to draw a line on the field slip. They can select the linestyle by changing the selections available in the form activated by button 11. The style in use is written on the button.
10. **Streaming - Turn on/off streaming** - Streaming adds vertices as your pointer moves around the screen whilst in editing mode. If you prefer to tap to add vertices, turn this off, else turn it on for streaming. You can set streaming preferences using the editing options button described in 6r below and detailed in section 3.4.7.
11. **Change GeoLine/ GeoPoly symbology** - This button allows the user to amend the symbology of a selected feature. The symbology is updated to reflect what is visible in the combo boxes (buttons 8 and 9).

12. **Label a geofeature** - When a feature (GeoPoly or GeoLine) has been selected, the user can use this tool to label it. To display the labels on the Map Face, select button 6n (see below).
13. **Edit Tool** - This allows the user to edit the shape of a GeoPoly or GeoLine by moving the shapes vertices.
14. **Activates the ink tools** - see section 3.3.3 below.
15. **View Old DFDC Projects** - This button allows the user to view old DFDC projects.
16. **Change style of GeoPoly/GeoLine** - This combo box shows all of the styles currently in use by the project. Select the style you want from the drop down box, select a feature to convert and click 'Go' (button 17).
17. **Convert style of GeoPoly/GeoLine** - Once an appropriate style has been selected from the combo box to the left (16), click the Go button to convert the selected GeoPoly/GeoLine.

3.3.3 Ink Tools

These tools can be accessed by clicking button 14 on the BGS DFDC toolbar.




1. **Draw ink** - The draw ink tool, also referred to as the Ink tool, is used to create ink graphics on the map. You can choose from several styles of pen ink from the drop down menus.
2. **Erase ink** - The erase tool removes all connected pieces of ink that you touch with your pen, including ink created with the draw ink tool. To erase ink drag the eraser across the ink you want to erase. If you wish to convert ink to shapefile, care should be taken when using the eraser tool. Try not to rub out in the middle of lines, but rub out from the ends.
3. **Select tool** - This tool enables the user to select graphics. Use this to select a committed ink graphic in order to re-activate it using the re-activate tool. When you select a graphic the project will automatically change the view to the same scale at which the ink was originally captured, and pan so that the graphic is in the centre of the screen. The ink tools within ArcMap are still fairly primitive, and this action prevents the graphics from randomly disappearing from the map.
4. **Reactivate ink graphic** - The Reactivate Ink button re-creates an ink sketch from a selected ink graphic element. You can reactivate an ink graphic that has been committed as a graphic and use the ink and erase ink tools to alter the graphic before you commit it to shapefile. Once a feature has been committed to shapefile it cannot be re-activated.


5. **Changes the style of the selected graphic element** - If you want to change the style of a committed graphic, select the line type from the combo boxes and click 'Go'.
6. **Convert ink to GeoLine or GeoPoly tool** - Converts ink of selected graphics into a line or polygon geometry (i.e GeoLine or GeoPoly) as defined in the adjacent combo box.

3.3.4 Main Menu


The main menu toolbar includes all menus found in any new ArcMap document, and some addition menus to use within BGS·SIGMAmobile.



1. **Save** - Saves the project
2. **Add layer** - lets the user browse to add a new layer into the GIS.
3. **Launch editor toolbar** - launches the editor toolbar to allow users more freedom with editing.
4. **GPS tools** – ArcGIS GPS Tools.
5. **DFDC project details** - menu of project/person specific buttons which change default settings.




- 5.a. **Set map face note style** - Use this to change the colour of the text and arrow of future map face note. Each time the project opens, the default is reset to a black arrow and black text. There is a choice of three styles.




- 5.b. **Populate User dictionary** - This button opens a form in which the user can change the default project details. This should be done by the data manager before going into the field, but in case it isn't, a user can populate the project details here.
- 5.c. **Project/User details** - This button displays the default project name and user details that have been entered into the database. Click this to change the user name, or check to see the details are correct. It is the same form as the one which pops up when the BGS·SIGMAmobile application is opened.

- 5.d. Use default GeoPoly styles** - By clicking this button, the default fill types and label text for the GeoPoly layer are applied. This removes any project specific customisation of value labels which may have been applied (see 5e).
- 5.e. Change Geopoly symbology labels** - This button opens the symbology window of the GeoPoly layer. A user can enter an alternative label for each polygon fill type into the label section. The value field must not be altered as the application colours the polygons based on the value field rather than the label field. The value fields are also used to construct the drop-down menu boxes for polygon fill-type, so it is important to note that even though you may change the label field, the dropdown menus will not change.




User changes symbology label here

Both the Value text and the Label text are stored within the attribute table of the GeoPoly layer. This is to ensure that project specific fill types can be retrieved with their true meaning at a later date.




6. DFDC tools, drop down list of tools (see list of buttons 6a – 6r below)



- 6.a. Finish Sketch** - If you are creating a GeoLine or GeoPoly feature and find it difficult to double tap on the tablet to finish drawing, click this button instead and it will finish drawing for you.
- 6.b. Turn on/off streaming** - Streaming adds vertices as your pointer moves around the screen whilst in editing mode. If you prefer to tap to add each vertex, turn this off, or else turn it on for streaming. You can set streaming preferences using the editing options button described in 6.r and detailed in section 3.4.7.
- 6.c. Delete Features** - This button allows the user to delete selected features.
- 6.d. Undo** - This button undoes the last action.
- 6.e. Redo** - This button redoes the previously undone last action.
- 6.f. Modify Geofeature** - When a GeoLine or GeoPoly is selected, the user can select this tool to automatically start modifying the look of the feature.
- 6.g. Delete Vertex** - ArcGIS editing tool that is also accessible by a right click, this option lets the user delete a vertex on a polygon.
- 6.h. Insert Vertex** - ArcGIS editing tool that is also accessible by a right click, this option lets the user insert a vertex to a polygon.
- 6.i. Split** - ArcGIS editing tool. This allows the user to split a geoline into two given a specified length.
- 6.j. Save Edits** - This button allows the user to save any edits without having to stop editing. It should be used regularly during an editing session.
- 6.k. Stop Editing** - This button forces the user to stop the edit session. If you have created or edited features, it will ask you whether you wish to save your edits.

6.l. Snapping - Opens the snapping window where the user can choose the part of the feature (vertex, edge, or endpoint) to which they want their new feature to snap. Snapping can be set for each layer loaded in the TOC.

6.m. Change vertex size - Allows the user to change the size of the vertex editing square to aid drawing.




6.n. Back Up Graphics - Backs up any graphics to the graphics feature class in the DFDC.mdb. The graphics are stored in the database as well as in the map

6.o. Turn labels on/off – If you have entered any labels for the GeoLine or GeoPoly layers, or want to view the notebook point labels, this turns labelling on or off.



Select the layers that you wish to view with labels. To add a label to a GeoLine or GeoPoly feature, use button 12 on the BGS DFDC toolbar and turn on the layers labelling option here.







If a layer's labels do not appear to correspond to the correct attribute field, right click on the layer to open its properties. Go to the labels tab and check that the label field is set to LABEL as shown here.

- 6.p. **Toggles status bar** - This button toggles on and off the status bar to create more room on the tablet to view the field slip. The status bar holds information about location and tool messages.
 - 6.q. **Reset DFDC Toolbars** - If there are several toolbars displayed in the GIS, click this button to hide all those except the main BGS·SIGMA*mobile* toolbars.
 - 6.r. **Editing Options** - This button opens the editing options form. Settings such as streaming tolerance can be adjusted for user preference here.
7. **Reset DFDC Toolbars** - If there are several toolbars displayed in the GIS, click this button to hide all of those except for the main BGS·SIGMA*mobile* toolbars.

3.3.5 Maximising the map display (data view)

In order to maximise the available screen space for viewing the digital field slip, a number of buttons have been created within the BGS·SIGMA*mobile* GIS.

- To turn off viewing the TOC click this button  (BGS DFDC Tools button 17).
- To turn off the status bar click this button  (main menu button 6.p).
- To reset all the toolbars click this button  (main menu button 6.q or 7).
- The Windows task bar can be set to auto hide. Right click on the task bar, select properties and check auto-hide.



Wasteful use of screen space

Optimal use of screen space

3.4 USING THE DIGITAL FIELD SLIP


Field mapping can consist of the following types of data recording:

- Pro-forma based recording - structured data which are commonly dictionary constrained.
- Notebook based recording - freeform recording of detailed comments and sketches (e.g. The Red Notebook).
- Map based recording – brief text notes on the map face, geological lines and landforms (e.g. the field slip).


BGS·SIGMA*mobile* has incorporated all of these types of recording into a digital environment. The GIS map acts as the field slip for map based recording of geological line work, landforms and brief text notes. Points that require further detailed comments or structure based recording can be marked on this digital map and expanded upon through the digital notebook.


3.4.1 The Map Face Note


The map face note is designed to replicate the traditional brief comments geologists make on their field slips. These are notes that are viewed on the map whilst conducting fieldwork.


To add a map face note to the GIS, click the Add Map Face Note tool . There are two clicks required to position the Map Face Note; the first positions the arrowhead and the second positions the end of the arrow at the start of the note. Once positioned, the Enter Map Face Note menu will appear in which you can add your note and tag your note with a topic to which it refers. More than one topic can be entered.

Hold the stylus over the box where the notes are to be added and the icon for the text input tool will appear. This allows users to select an onscreen keyboard or handwriting input.



The map face note will appear in ArcMap. It can be moved around or resized using the edit annotation tool. 



To edit a note you have created you must first select the annotation feature you wish to edit, then click the edit Map Face Note icon . This will open the Edit Map Face Note form as before, but this time the tags and comments previously entered will be displayed. Change the tags or note and click save edits. The edit annotation button is automatically turned on so that you can now move the annotation.

When annotation is created or edited, BGS·SIGMA*mobile* automatically stores the username and the date in the annotation attribute fields. The note itself is also stored here. The size of the annotation is set so that it can be viewed and read at the quarter sheet level for 1:10,000 mapping – the size of a BGS field slip. The text therefore may appear quite large when zoomed in, or too small if zoomed out.

When creating map face notes, it is important to bear in mind that the enter key must be clicked to create a new line within the note. This is true on the tablets even if using the hand writing recognition where text wraps to a new line.

The following QA attributes are stored within the Map face note attribute field:

TextString	Date_Made	Date_Modified	USER'	Front_TAG	end
Boundary uncertain	18/04/2006 15:57:42	18/04/2006 15:57:42	.	<MAPFACE NOTE><STRATIGRAPHY>	</STRATIGRAPHY></MAPFACE NOTE>

Record: 0 | Show: All Selected | Records (1 out of 1 Selected) | Options



There are three different Map Face Note Styles available: Black Arrow with Black Text, Orange Arrow with Orange Text, and Purple Arrow with Black Text.

There are two ways to modify the style. To change the Map Face Note Style for the next map face note go to the DFDC Project Details Menu and choose Set Map Face Note Style. Note that this does not change the style of any previously placed map face notes.

To change any other map face note styles – right click on Map Face Note in the Table of Contents to open the Attribute Table. Under SymbolID* change the number to reflect the style: Black = 20, Orange = 23, and Purple = 24. To change many records: Select the records, right-click on SymbolID*, Field Calculator, in the SymbolID= box, type 20 (or 23 or 24 depending on the style you require).

Map Face Note X and Y values are automatically updated when the document closes.

3.4.2 The Notebook Point Observation

Notebook points can be added to the digital field slip when more detailed or structured information is required about a certain point. There are two buttons which access the digital notebook.   The green flag allows the user to add a notebook point; the red flag allows a user to edit an existing notebook point. Notebook points are labelled on the map face with the username and a consecutive number so that the geologist can reference it. It is also possible to add a summary label in to the digital notebook to summarise the notebook entry if required. For example, if the lithology is

Mercia Mudstone then the geologist may wish to write the summary label MM. The method in which you would create this summary label will be outlined in section 3.5. These summary labels are shown in red as indicated below. To view these in the GIS, the map must be refreshed and the layer label option turned on.

● USER1_10_10MM

It is important to be patient with the system when adding or editing a field observation. It takes a small amount of time for the code to be generated to open Access from within ArcMap and transfer and build the relevant forms for data entry.


To delete a notebook feature ensure the layer is open for editing. Select the feature and click delete. Note that the database has been set to cascading so any associated notes in the database will also be deleted. Use the Undo button (6.d) to restore (undelete) the data.

ArcMap has been customised so that when it shuts down, all X and Y attribute values are updated in case any feature has been moved within the session.

To move a Notebook point observation: Go to Editor > Start Editing > OK. Using the ‘Select Elements’ tool hold the cursor over your new location and write down the coordinate location from the bottom right of your screen. Set the Task on the Editor Toolbar to Modify Feature, Select the Field Observation Point to be moved, right-click and select Move To. Enter the X and Y coordinates of your new location. The new coordinates will also have to be updated in the Attribute Table. In the Table of Contents, right-click on the Field Observation Point, Open Attribute Table, and enter the new coordinates in the X and Y fields of the selected Field Observation Point.

Observation Point Trouble Shooting: You have made a selection with the ‘Edit Notebook observation point’ tool and received the following message: “You have not made a selection.” This may be caused by broken links (red exclamation marks) in the Table of Contents (in ArcMap) or the Field Observation Point layer (from either the current DFDC or the old DFDC) is not switched on. Repair the links by clicking on the red exclamation mark and re-setting the source and make sure all Field Observation Point layers are on and visible.


3.4.3 Reviewing Notebook Data within ArcMap – Précis Tool



The green information button  (Précis Tool) shown as button 7 on the BGS_DFDC toolbar enables the user to view the contents of the notebook for each field observation point. The Précis Tool can also be accessed through the DFDC database. General Information is displayed at the top of the form with more detailed information contained in tabs below. Photos and Sketches are viewable and selected using the Film Strip view at the bottom of the form and can be individually rotated.


Precis of CurrentLocation



3.4.4 The GeoLine Tool





The GeoLine tool  is designed to add geological linework onto the digital field slip. The user selects the tool and draws the line style displayed on the tool. The line style is chosen using the set line style tool.  The following menu will appear. Select the Line tab.



The tool will remember the last selected line style during the working session. The line style selected will appear in the tool name field.

Streaming can be turned on or off (see section 3.4.7) and vertices can be removed using the edit vertices tool. The size of the editing vertices can be altered by using the change vertices size button.

If a GeoLine feature has been drawn using the wrong style it can be amended. Select the line you want to amend, select the required style from the drop down menu, and click Go to attach the correct attribute values. 


To add a label to a GeoLine feature, select the feature and click the  button. A comments form with tags will be shown. This form is the same as the Add Map Face Note form except the size of label is limited to 50 characters. This allows the label to be tagged with a topic if required. To view the labels, make sure that the GeoLine layer labelling is turned on using the turn labels on and off button.



The attribute table for the GeoLine is shown below.


OBJECTID*	Shape*	LINETYPE	LABEL	Date_Made	Shape_Len	USER_ID*	Front	End_TAG	Date_Modified
4	Polyline	Fault	inversed	18/04/2006 16:33:00	180.612056	Test	<MAPFA	</STRATIC	18/04/2006 16:33:41

It is also possible to create GeoLine features using the graphic ink tools. This is described in section 3.4.6.


3.4.5 The GeoPoly Tool





The GeoPoly tool  is designed to delineate and draw polygon features onto the digital field slip. The user selects the tool and draws the polygon style displayed on the tool. The polygon style can be set using the set polygon style tool.  Select the Polygon tab on the following menu.



Alternatively, if the project has preset project fill styles, the menu may look as follows:



If a GeoPoly feature has been drawn using the wrong style it can be amended. Select the line you want to amend, select the required style from the drop down menu, and click Go to attach the correct attribute values. 

To add a label to a GeoPoly feature, select the feature and click the  button. This form is the same as the Add Map Face Note form except the size of label is limited to 50 characters. This allows the label to be tagged with a topic if required. To view the labels, make sure that the GeoPoly layer labelling is turned on using the turn labels on and off button.


The GeoPoly attribute table is shown below:

OBJECTID	Shape	POLYTYPE	PROJECTTYPE	Date_Made	LABEL	Shape_Le	Shape_Area	USER_ID	Front_TAG	End_TAG	Date_Modified
1	Polygon	Black Backwards Diagonal	Made ground	18/04/2006 14:49:18	flat	10267.6624	6345087.97361	TEST	<MAPFACE	<JSEOMOR	18/04/2006 14:49:18

Record: 1 Show: All Selected Records (0 out of 1 Selected) Options

It is also possible to create GeoPoly features using the graphic ink tools. This is described in the following section.


3.4.6 Using the Ink Tools



The BGS·SIGMA*mobile* development team have developed the existing ArcGIS tablet tools to allow users to draw graphic features using freehand tools as they would with a pencil and rubber. **The Ink Tools tools are included in this release of BGS·SIGMA*mobile* but need to be used with care as the core development of ink tools within ESRI software is still being developed.**


The tools can be used in the following stages:

1. Click on the pencil button and draw graphic ink on screen. Move the stylus away from the screen to complete the graphic.




Use the line thickness and colour options from the two drop down lists to change the pencil line style.


2. Once the ink sketch is completed decide whether you want to commit it to the database as a GeoLine or GeoPoly feature or whether you want to temporarily store it as a graphic within the BGS-SIGMA*mobile* .mxd project. If you are satisfied with the ink sketch and want to store it as a GeoLine or GeoPoly feature then select a GeoLine or GeoPoly style from the lower drop down box and click Go.




3. If you have selected a line feature style the element will be converted into a GeoLine feature and stored in the database. The feature will be symbolised with the symbology of the selected line style.
4. If a polygon style is selected from the drop down box, even if the ink sketch is not a closed feature, the tool will convert the sketch to a polygon closing the polygon across any gap. The created GeoPoly feature will be symbolised with the symbology of the selected polygon style as in the image below.




5. If you are not ready to convert this feature, you can temporarily commit the sketch to the graphic layer in the ArcGIS .mxd project to re-activate it later. To commit the element to the graphics layer either start using another tool or close the Ink Tools and save the project. Note that the element will not be stored in the database; it will not have any attributes and will not be transferable into another GIS. In the event of the .mxd becoming corrupt, data captured in this way, without conversion to a database feature is likely to be lost. **Users should therefore only temporarily store data as a graphic, with the requirement to convert them to database features as soon as possible (preferably before the end of the editing session).** If you do not do this, it is imperative to keep a regular back up of your .mxd on an external device such as a data stick, external drive or another PC.

6. The eraser tool  allows part or the entire graphic to be erased.

- To re-select a stored ink sketch, open the Ink Tools window, click the arrow button and select the graphic. Once the graphic is selected, click on the refresh  ink button. As a function of the software the map will refresh and redraw a number of times. Be patient while this happens as repeatedly clicking the map may cause BGS-SIGMAmobile to crash. Once the graphic is re-activated the eraser tool or the pen tool can be used to refine the sketch. Be careful to just rub out the edges of the line rather than the middle because this may affect the conversion to shapefile. If in doubt, create a new ink line to draw over your edits and use this to convert to shapefile. **Note: The view will automatically change to the same scale at which the ink was originally captured, and pan so that the graphic is in the centre of the screen. The ink tools within ArcMap are still being developed, and this action prevents the graphics from randomly disappearing from the map.**


Ink Tools trouble shooting: On some hardware systems, if the system has been on Stand-by mode you may start to experience the ‘invisible ink phenomenon’ where no element appears when it is being drawn. This is a known issue and the solution is to close all programmes and re-boot the machine for the tool to work correctly again.

3.4.7 Editing Options (Stream or Point Mode)

GeoLine or GeoPoly features can be created in two ways; point mode or stream mode (streaming). You can switch back and forth between the two modes as you digitise by clicking the streaming button  Streaming (main menu button 6b).

When you start creating a feature on the screen, the default mode is point mode. This enables the user to create a feature on the map using a series of points. The user taps on the screen to create each new point.

Stream mode capture lets the user capture features by automatically adding vertices at an interval specified in the stream tolerance section of the ArcMap editing options. The default ArcGIS stream tolerance is normally zero, although in BGS-SIGMAmobile it has been set to five. Each user must enter a tolerance value that suits their requirements. If the tolerance is set to zero, the vertices will join together or overlap each other. The stream tolerance can be changed at any time, even when in the process of creating a feature. The user should adjust these options to their own preferences using the Editing Options dialogue, available via the Editing Options Tool (6.r).



The user can also define the number of streaming vertices that they would like to group together. This number tells ArcMap how many vertices to delete when the Undo button is clicked. For example, if this number is set to 50 and the Undo button is clicked whilst the feature is being

created, ArcMap deletes the last 50 digitized vertices from the feature. This value is set to 10 as default in the BGS·SIGMA*mobile* GIS.

Sticky move tolerance can also be set here. This setting determines the minimum number of pixels the pointer must move on the screen before a selected feature is moved. This reduces the risk of moving a feature by accident.

Other ArcGIS specific editing tools, such as inserting vertices, have been incorporated into the DFDC Tools drop down list many of which can be accessed by right-clicking. Additionally, for those users who dislike right-clicking, these tools have been included in the drop down list as well.

3.4.8 Viewing Old DFDC Projects


This button allows the user to view old DFDC projects. These projects are not actually loaded into your current database (DFDC) but become viewable in one .mxd from their separate locations. Older databases can be both queried and viewed using the BGS·SIGMA*mobile* tools available in your current project but should not be edited. It should also be noted that the précis tool, new to 2009A, will not be usable with these files.

Before uploading any old DFDC projects you must rename that database in Windows Explorer or ArcCatalog (this tool will not upload a file called DFDC as one already exists within the project). A suggested naming convention might be ProjectName_Field Date_UserID_DFDC.mdb. When the button is clicked, a ‘Select Database’ dialog box will appear, browse to the database to be used, and click OK. The Project will then take a few seconds to load.

3.5 CAPTURING STRUCTURED DATA OR DETAILED OBSERVATIONS

BGS·SIGMA*mobile* data is structured and data is recorded in a set of related tables in Microsoft Access. A Microsoft Access 2003 database can hold 20GB of information. Once this limit is reached, it will not store any more. There may be a loss in speed the more data is in the database.

3.5.1 Layout of the Notebook form



The notebook application is designed to fit a 12.5cm by 17cm screen in landscape format. It is accessible via the add notebook point button or the edit notebook point button in ArcMap.

- 1 Creation of unique user ID (UUID) and site label to be displayed on the GIS. This is done automatically when the observation point is created.
- 2 Top level information. Much of this is populated automatically. This is detailed below.
- 3 Switch form offering the modules available in BGS-SIGMA*mobile* for data capture.
- 4 Buttons to add comments, sketches, photos or samples at any point in application.
- 5 The user can tell where in the system they are from this message. FOP means you are at the top Field Observation Point level, FOP_SPOT_LITH_2 would tell you that you were in Spot, lithology number 2. The sketch, sample, photo and comment areas record where in the notebook they were activated. So if a sketch were now drawn in FOP_SPOT_LITH_2, it would record that it was a sketch relating to Spot, lithology number 2.
- 6 General Tools including Photo Transfer, Photo Collection Spreadsheet and Précis of the Current Location.

3.5.2 Top level information

There are six tabs where data can be entered about the observation point.

The screenshot shows the 'frmFieldObsEntry : Form' window. The title bar reads 'frmFieldObsEntry : Form'. The main window has a yellow header with 'Field Observation Entry' and 'Locality No' set to 'Test_12'. To the right, there's a dropdown for 'FOP' with '76' selected. Below the header, there are several tabs: 'Locality Desc and Summary Label', 'X Y and Z values', 'Project Scale Field Slip', 'Management Fields', 'Housekeeping', and 'Geologist Info'. The 'Locality Desc and Summary Label' tab is active, showing 'Loc Desc.' as 'At foot of slope' and 'Sum. Lbl.' as 'MM'.

In the Locality Desc and Summary Label enter a location description and a summary label to summarise the notebook entry. This can be viewed on the field slip in red ink as described earlier in section 3.4.1.

This screenshot shows the 'Field Observation Entry' form with the 'X Y and Z values' tab selected. The header shows 'Locality No' as 'Test_12' and 'FOP' as '76'. The 'X Y and Z values' tab displays the following information: Easting: 73083.432, Northing: 901454.725, Ref Sys: BNG, XY Src: Map, Z Value: (empty field), and Z Src: (empty field).

The X, Y and Z values tab displays the easting and northing of the notebook point you added or are editing. This is automatically generated by ArcMap when the point is added. A note of caution – if you move a point by editing it in ArcMap, the X and Y values in the attribute table will not automatically update to the new location. They will need to be edited in the attribute table to show the new X and Y location of the geometry.

Enter the Z value if known and how you obtained this Z value in the Z source field.

This screenshot shows the 'Field Observation Entry' form with the 'Project Scale Field Slip' tab selected. The header shows 'Locality No' as 'Test_12' and 'FOP' as '76'. The 'Project Scale Field Slip' tab displays: Field Slip: NA70SW, Scale: 1:10000, Project: E2033574, and Data Source: (empty field).

The Project Scale Field Slip values were all automatically entered within the GIS. You cannot edit them here, just view them. Enter more information about the X, Y or Z data source in the field.

This screenshot shows the 'Field Observation Entry' form with the 'Management Fields' tab selected. The header shows 'Locality No' as 'Test_12' and 'FOP' as '76'. The 'Management Fields' tab displays: Obj ID: 76, Date: 18/04/2006 16:48:10, Geol: Test, UUID: Test 18042006164810, Principal Source: PFO, and Loc No: Test_12.

The Management Fields tab is used to confirm the date and geologist code are correct. These cannot be edited. PFO stands for Primary Field Observation. All data collected in the field will have this value.

Field Observation Entry Locality No Test 12 18042006164810 FOP 76

Locality Desc and Summary Label X Y and Z values Project Scale Field Slip Management Fields Housekeeping Geologist Info

Edit Collector/Sample no View Manipulate Dictionaries View Precls of FOP Show Menu

The Housekeeping tab is used to perform several tasks quality assurance tasks. Dictionaries can be customised (see section 3.5.16 for more detail), sample numbers can be entered (see section 3.5.14), a text display of the notebook entry can be created (see Appendix), and the main menu in Access can be shown or hidden to create more space on the system. This latter task is achieved by clicking the Show Menu button.

Field Observation Entry Locality No Test 12 18042006164810 FOP 76

Locality Desc and Summary Label X Y and Z values Project Scale Field Slip Management Fields Housekeeping Geologist Info

Collector id Test Last Sample No 242

The Geologist Info form stores information important to the geologist. The geologist can enter their Collector codes here. The collector code may differ depending on what type of sample is being made. You can also enter the starting sample number to ensure that the sample is unique and matches your sample labels.

3.5.3 Spot Observations

A spot observation is a two dimensional log (think of a log which only comprises one unit). An example of a spot observation would be brash. The types of measurements to record are dependent on the type of spot observation you are making. The example below shows the measurements you may make for brash.

Σ Mobile Spot Observation (designed and built by BGS)

Spot ID (New) Object UUID #Error Search for Lith > Loc no #Error

General Weath, Altern, Strength Lithology, Interp, Crono, Strat Grain Size CACO3/Moisture/Organic Mineral/Textural Till Fabric

GENERAL SPOT OBSERVATIONS

Type Not Entered Lithology: ?


Size m. 0.00 +/- 1 +/- 10 Lith Colour: Not Entered

Derivation Not Entered Stratigraphy: Not Entered PARENT DATA NOT YET E

Abundance

Record: 1 of 1 No Filter Search


You can take several measurements or make descriptions here about the spot observation by clicking on the tabs entitled Grain Size etc. to open the individual forms.




In the above example, the orange area highlights the two lithologies entered for a spot observation, one for mudstone and the other for clay. The pencil symbol on the grey column is highlighting the second lithology and any sketch, photo, sample or comment taken now would relate to lithology 2 - clay. To navigate through different lithologies, either use the scroll down list or use the default Access record mover in the lithology section.

The area shown in orange in the diagram above lets the user enter information relating to the lithological distributions within the unit as a whole. The unit thumbnails also store information about the whole unit, whereas the lithology thumbnails just store information about the lithology within the unit.

The system gives the user flexibility to write information (such as grain size, and CaCo3 content) pertaining to the whole unit or just a particular lithology in the unit. The user must decide in the field, which is more appropriate.




The example above shows how grain size information may be entered about the whole unit.



Whereas this example shows how a user may enter grain size information about the second lithology in the unit.

3.5.4 Structures



Enter information about structures in this section of the notebook. Again, relevant boxes and dropdown lists for entering data will appear in the form depending on the type of structural measurement being made in the field. Also the GeoLine, GeoPoly or Map Face note tools can be used in the digital field slip to augment the information. Note that the Dip-Azimuth can be recorded directly or it can be calculated from the Strike/Dip information by clicking in the compass tick boxes. Multiple structures can be recorded using the >* button at the bottom of the window, and the measurements can be symbolised automatically with the correct azimuth by following the instructions in Section 3.6.

3.5.5 Landforms (glacial)

LANDFORM_ID: 2 OBJECTID: 36 UUID: KIGL30032007174416

Landform Type: Erratic GSD Comment:

Lithology: Calcareous mudstone

Length m: 2.000 +/- 1 +/- 10

Width m: 1.000 +/- 1 +/- 10

Height / Amplitude: 0.000 +/- 1 +/- 10

Record: 1 of 1

Enter information about glacial landforms in this section of the notebook. The measurements made in the field are dependent on the landform type being recorded. Depending on the value entered in the Landform Type field different boxes will appear to enter subsequent values.

When developing the data model, all landforms were considered, but only those landforms that would actually be measured in the field were included in the system. Other landforms, or the extent of a landform should be recorded using the GeoLine, GeoPoly or Map Face Note tools.

More than one landform can be entered at any one point by clicking the record arrow at the bottom of the Landforms form to navigate to a second record. A record can be deleted using the delete button.

3.5.6 Sections

Logs (augers, sections, quarries etc) can be entered in this section.

Basic Field Section Tool

Edit/Create Log Type: Direct Log Name:

Log Azimuth: 0 Log Incl.: 90

Sort Log	First Lith	Code	Rel Abund	Colour	Free Text	Base Limit	Thickness
0	Not Entered	Not Entered				Not Enter	

Record: 1 of 1

By clicking the Sort Log Units button, the order of units can be sorted in the correct order so that the user can sequence through the log from top to bottom correctly using the unit record arrows

For each unit any number of lithologies can be entered, and information, such as grain size, about the unit as a whole, or a lithology within the unit, can be entered in a similar manner as described in the spot observations section.

3.5.7 Viewing the log tools

The screenshot shows a window titled 'qryShowBasicLog' with a 'LOG_NAME' field containing 'Test_3_LOG_1_AUGERH' and a 'Close Form' button. Below is a table with the following data:

Order	Lith Code	Lith Proportion	Lith Colour	Relationship	Thickness
1	Clay	Primary	grey, dark	Not Ente	0.450
2	Aggregate	Primary	Not Enterec	Interbed	0.230
2	Alkali Metabasalt	Secondary	Not Enterec	Interbed	0.230
3	Clay	Primary	grey, dark	Interlamii	0.300
3	Cobbles	Secondary	grey, orange	Interlamii	0.300
4	Clay	Primary	grey, dark	Not Ente	0.400
5	Clayey Sand	Primary	Not Enterec	Not Ente	0.300

At the bottom of the table, the 'Cumulative Thickness' is displayed as 1.68. Below the table is a record navigation bar showing 'Record: 7 of 7'.

At any point whilst creating units within a log, the user can click the View/Edit Log button. When this button is clicked, the form shown above will appear. In the example above, the user has edited the order fields so that they are numeric 1 – n. Where there are two orders of the same number, it signifies that there are two lithologies recorded for one unit. For example, unit 2 above has both Aggregate and Alkali Metabasalt. The form shows the log from top to bottom and lets the user edit some of the main details about the log.

The log viewer, shown in the image above, lists the thickness of each unit and adds these thicknesses together to give a cumulative thickness. If there are two lithologies within a unit it displays the thickness of the whole unit for both these lithologies. For example, for the unit ordered number 3, there are two lithologies; Clay and Cobbles. Unit 3 has a thickness of 0.3 metres. This 0.3 metres is written beside both lithologies. However, only one 0.3 metres is included in the cumulative thickness of the log as 0.3 refers to the whole unit not the lithology.

3.5.8 Full Log and Sections Tool


Documentation for this tool is still in preparation along with instructions on full log data capture.

3.5.9 Landslide Observations


Documentation for this tool is still in preparation along with instructions on landslide data capture.

3.5.10 Setting the correct location, before entering comments, sketches etc

The user can ensure that they are entering a comment, sketch, photo or samples about the correct feature by ensuring that the black bold text displayed in the top right hand corner of the notebook reads what the user wants to relate the comment, photo, sample or sketch to. The following images show different scenarios depending on which part of the form the user has last used. The black filled columns are a useful guide to this, and if the user clicks within these areas, the text in the top right hand corner of the notebook should change.



Indicates that the comment etc will refer to the field observation point (FOP) as a whole



Indicates that the comment will refer to the fourth Spot observation recorded in the database.

Indicates that the user is viewing the first of two spot observations at this site.

Field Observation Entry Locality No Test_11 19042006140634 FOP_SPOT_LITH 3

Loc Desc. Barnfield farm Sum. Lbl. MM

Spot Observation Log Glacial Landform Structure

SPOT_ID 4 OBJECTID 11 UUID 19042006140634

General Weath, Altern, Strength Lithology, Interp, Crono, Strat Grain Size CaCO3/Moisture/Organic Mineral/Textural Till Fabric

LITHOLOGY OBSERVATIONS

Lithology Colour Proportion Grain Size Grain Dist Sort Spher Ang CaCO3 and Moisture

3 Albite Felsite Proportion 1 Colour olive, dark Relation

* Lithology Colour Proportion Grain Size Grain Dist Sort Spher Ang CaCO3 and Moisture

ber) Proportion NOT ENTEI Colour Not Entered Relation

Record: 1 of 1

UNIT INTERPRETATIVE LIMITS AND TEXTURES OBSERVATIONS

Stratigraphy: Not Entered PARENT DATA NOT YET ENTERED Limit Top: Limit Bottom:

Chronostrat: NOT ENTERED Texture Abundance: Texture Feature:

Geometric Form: Not Entered Texture Distribution:

Deposit Environment: Not Entered

Record: 1 of 2

Indicates that the comment etc will refer to this lithology – the 3rd recorded in the database.

Indicates that the user is viewing the first of only one lithology recorded for this, the first of 2 spot observations, at this site.

3.5.11 Comments

frmComment : Form

Enter Field Observation Comment LO Test_2

ID:	Comment Associated With	no.	COMMENT:
1	FOP_LANDFORM	1	This would make an interesting place take a borehole
* mber)	FOP_LANDFORM	1	

Select Suitable Tags

COMMENT_ID	TAG
1	

Record: 1 of 1

Comments can be made at any point in the system. The position where they were called from is documented automatically. This will be the location the comment button was clicked in and will relate to the value displayed in black bold text in the top right hand location of the notebook as discussed in section 3.5.1. Each comment made should be tagged with an appropriate topic tag. More than one tag can be used for any one comment.


3.5.12 Sketches

ID	Sketch Associated With	no.	Comment	
1	FOP_LANDFORM	1	Looking South	Create or Review/Edit Sketch
* per)	FOP_LANDFORM	1		Create or Review/Edit Sketch

Record: 1 of 1

Sketches can be added or reviewed from the notebook at any point by clicking the sketch button. The form shown above will open in which you can add or edit a comment about your sketch. The position where the sketch was called from is documented automatically. This will be the location the comment button was clicked in and will relate to the value in black bold text in the top right hand location of the notebook as discussed in section 3.5.1.


Sketches are created using a customised version of Agilix infinotes called the BGS Sketch Tool. This programme needs to be installed separately from BGS-SIGMAmobile. The drawing tools are very simple to use.



3.5.13 Photos


Metadata about photos taken in the field can be added through the photo forms. The photos will remain on your camera until you upload them to your PC. Use the Photo Transfer facility on the database start up screen. This is detailed below.



3.5.13.1 PHOTO FORM

The database requires that you first enter a description of the photo. Once you have entered this you can link to a photo if it is already on your tablet, by clicking the photo button on the form . There is no need to rename the photos as the database will do this automatically. It will also copy the renamed photo to the Photographs folder in your BGS·SIGMA*mobile* directory and make the necessary linkages automatically.

If you have linked to a photo you can view it by clicking on the ‘view photo’ button. If your photos are not yet on your PC you can go back and transfer them to the BGS·SIGMA*mobile* database at a later date.

The new file name assigned to a photograph consists of the LOCALITY NUMBER plus the current date and a number which starts at 1 for each locality. The original file name is also preserved in the Film Frame database table field. It is recommended that photos are transferred as often as possible.



ID	Photo Associated With	Photo Filename	Description	
1	FOP	Test_2_06032008_1	Looking North	
*	FOP			

3.5.14 Samples

Before taking samples using the BGS·SIGMA*mobile* system, each geologist must set up a Collector code number in the database on the system. This is done through the housekeeping section of the notebook. If a user is returning to the field the start number can be set to any value.



Locality Desc and Summary Label | X Y and Z values | Project Scale Field Slip | Management Fields | **Housekeeping** | Geologist Info

Edit Collector/Sample no | View Manipulate Dictionaries | View Precs of FOP | Show Menu

The user should click the “Edit Collector/sample no” button before taking the system out in the field and make the appropriate changes to the form which is displayed below.

The Collector ID and the last sample number can be edited at any point and may change depending upon the type of sample being collected.

The numbers and ID's written in the above form should reflect the Geologist's user ID and sample number in their relevant sample book.


For information, the user can see the user name, ID, project details and map scale they registered in ArcMap. These should not be edited here unless absolutely necessary.

Once the "sample" button has been clicked you will see this pop up box:


Click Yes to continue to the form and enter any relevant information and No to exit.

3.5.15 General Tools

3.5.15.1 PHOTO TRANSFER

If the photos are not on your tablet you can link the photos to the correct metadata once you have uploaded them to your PC. To link to the photos like this, click on the Photo Transfer button on the opening screen of the database. The form will display a list of descriptions about the photos taken at that location. Click on the photo button  to associate a photo on your PC to the appropriate

description. There is no need to rename the photos as the database will do this automatically, as well as copy the renamed photo to the Photographs folder in your BGS·SIGMA*mobile* directory.



3.5.15.2 PHOTO COLLECTION SPREADSHEET

This button creates an excel spreadsheet in the photographs folder of your current working project. It exports the data in a format suitable for the BGS Photographic database. For this to work efficiently you must transfer and describe all of the photos in the database that are to be exported. It is recommended that you do this on a daily basis.

3.5.15.3 SAMPLE COLLECTION SPREADSHEET

This button creates an excel spreadsheet in the root of your current working project area. It exports the data in a format suitable for the BGS Collections Department to enter in to their systems. For this to work efficiently you must transfer and describe all of the samples in the database that are to be exported. It is recommended that you do this on a daily basis.

3.5.15.4 PRÉCIS OF CURRENT LOCATION

A specialized Précis Tool can be accessed using the information button in BGS·SIGMA*mobile* and within the Database itself. This tool is described in more detail in the Appendix.


3.5.16 Customising project dictionaries in the notebook

The user can select the dictionary values a project uses most often so that they appear at the top of a dictionary listing by clicking the View Manipulate Dictionaries button in the housekeeping section of the notebook, as shown below.




This action will open the following form. The user can select the appropriate dictionary to customise from the drop down list (combo box) and tick or untick values in the Project Control field depending on whether a value should be listed at the top of a dictionary list in the system. The

example below shows the values for the DIC_WEATH_WEAK dictionary that describes weathering.



The results of the above customisation can only be seen when the notebook application is re-opened. They can then be seen within the Weathering sections of the notebook (within the Spot or Log forms). The image below shows that the three values that were ticked in the dictionary browser above appear at the top of the drop down list. They are in alphabetical order. The other values are still included in the drop down list but now appear below those values where the user had indicated a preference in the Project Control field.




3.6 DISPLAYING STRUCTURAL INFORMATION IN BGS-SIGMA MOBILE

It is possible to display structural measurements taken within BGS-SIGMA mobile as a separate layer within the GIS and orientated in their appropriate direction. When you open BGS-SIGMA mobile you will see that there is a layer called Structure Events. This layer is an Event theme. It is created by adding the table called FOP_STRUCTURE from the DFDC.mdb into the GIS. The table is visible in the Table of Contents when the Source tab is selected.

3.6.1 Creating a Structure Event Layer

Follow the instructions below to set-up the Structure Events Layer:

1. Add in the FOP_STRUCTURE table from the DFDC.mdb
2. Right click on the FOP_STRUCTURE table in the Source tab of the TOC and select Properties to open the properties dialog box. Select the Joins/Relates Tab.
3. Right click on the FOP_STRUCTURE table in the Source tab of the TOC and select Joins and Relates followed by Join.




4. It is necessary to make a join to the FIELD_OBSERVATION_POINT based on the UUID in order to join the X and Y data to the FOP_STRUCTURE table. In the Join Dialog box that opens the following should be set:


Select the UUID field as the field the join will be based on.

Select the Field Observation Point table as the table to join to.

Select UUID as the field from the Field Observation table to use in the join.



5. Once the joins are made an event theme can be generated. To do this, right click on the FOP_STRUCTURE table and click Display XY data. The following menu will appear.




The X Field and Y Field attributes need to be assigned in order to display the points in the GIS.

- X value should be the FIELD_OBSERVATION_POINT.X attribute and the
- Y value should be the FIELD_OBSERVATION_POINT.Y attribute
- Make sure to set the coordinate system to be British National Grid.

Click OK and a FOP_STRUCTURE_FIELD_OBSERVATION_POINT Events layer will be added to the TOC.

6. To symbolize the structure layer:

- Open the Layer Properties for FOP_STRUCTURE_FIELD_OBSERVATION_POINT Events, select the Symbology tab and select Import.
- Browse to your Project Folder SIGMA_MOBILE_2009A and select Structural_Symbols.lyr.
- On the Symbology tab click the Advanced button and check that rotation is based upon the FOP_STRUCTUREAL_AZIMUTH field. Set the rotation to be the Geographic Rotation Style.
- To Label the Structures go to the Labels tab within Layer Properties – check on Label features in this layer and within Label Field select FOP_STRUCTURE AZIMUTH.



Once you have set this up once, it will be saved in your project and structural measurements will automatically appear in the event layers when you create them using the notebook point tool.

4 Using the BGS Integrated Tools

4.1 THE BGS COMPASS BEARING TOOL

The purpose of the tool is to show compass bearings i.e. lines of sight and backsight in ArcMap. The tool is a simple way for the geologist to use a compass to record a bearing to/from features on the landscape, and to draw lines of the same bearings onto the map.

To use the Bearing Tool select Bearing Tool from the list of toolbars available.

The Bearing Toolbar will then become visible:



Bearing Tool



After clicking the Bearing tool button, the mouse icon changes to a set of cross-hairs and the tool is ready to use. Single-tap on the screen where you wish to take the bearing from and hover the stylus elsewhere to see a dashed red line appear. The bearing of the line is displayed in the bottom left of the screen.

When you double-tap to finish the line, it becomes a solid line and is annotated with the compass bearing. The compass bearing is always displayed at the terminus of the line (i.e. where you double-tapped).

Delete Bearing Graphics



Clicking the Delete Bearing graphics button will remove the graphics created by the Bearing tool from ArcMap's map display. Note that any other graphics on the map display (that were not created by the Bearing tool) will not be removed.

4.2 THE BGS STRUCTURE CONTOUR TOOL

The purpose of the tool is to calculate Structure Contours to estimate where a geological bed will outcrop. Given the location of an Observation Point where the angle and direction of dip of the bed are known, and assuming the dip is uniform, the tool can calculate an equation for the plane of the bed. From this equation it is then possible to calculate the elevation of the bed at any point. By using a DTM this elevation can be compared with the ground elevation and where the two are equal it can be predicted that the bed will outcrop.

4.2.1 Using the Tool

1. Open the Structure Contour Toolbar (from the View Menu on ArcMap, select Toolbars and then click on Structure Contour Tool from the list of toolbars available).



The Structure Contour Toolbar contains the following three buttons:



Calculate Structure Contours



Delete Structure Contours




Save Structure Contours as Shapefile

The functionality of each of these buttons is described in detail below.

4.2.1.1 CALCULATE STRUCTURE CONTOURS

After clicking the Calculate Structure Contours button, the user is presented with the following window:




The user is required to enter four types of input: DTM, Observation Point, Tool Parameters and Search Area:

DTM

The DTM input consists of a dropdown menu that lists the raster layers available in the current project. Note that this list includes non-DTM rasters such as topographic maps or images. The user must select only the DTM layers to be used to calculate all elevation values by the Structure Contour Tool.


If the Search Area that you are interested in is likely to be covered by more than one DTM, click on the Multiple Layers as DTM button and you will be presented with the following window:



Make sure that all of the DTM layers that cover the Search Area are ticked and then click on the 'Back to Main Form' button. The value in the DTM Combo box will now be set to: Multiple DTMs.

Calculation method

There is an option to use one input point for structure contour calculation or up to three input points where there are known measurements. The user can input measurements for each known observation point as described in the Observation Point section below.



Observation Point

The Observation Point inputs consist of the observed properties of the bed at a known location. They include:

1. **Easting:** The National Grid Coordinate (Easting) of the point.
2. **Northing:** The National Grid Coordinate (Northing) of the point.
 - a. Easting and Northing values can be typed in manually or can be entered automatically by clicking on the required location on the map display. As the Inputs window is relatively large and obscures the majority of the map display, the button 'Switch to Small Inputs Form' has been provided. Clicking this button closes the main inputs form and opens the following window.



- b. Once this window appears the user simply clicks on the map display to input the coordinates of the structure measurement. When the correct values are entered, click on the 'Back to Main Form' button to return to the original Inputs window. Note that on returning to the main Inputs window the Easting and Northing values have been populated using those values selected using the smaller window.
3. **Elevation:** The elevation of the point in meters. This value can be typed in manually or populated automatically (after the Easting and Northing have been entered) by clicking on the Get Elevation from DTM button. This button uses the entered Easting and Northing values to query the selected DTM and returns the appropriate elevation Z value.

- 4. Dip:** The observed angle of dip of the bed. This will be a value between 0 and 90 degrees and can be typed in manually or populated using the slider to the right of the Dip text box. To move the slider by a factor of one degree, click just to the left or to the right of the slider's pointer and it will move 1 degree in that direction.
- 5. Azimuth:** The observed direction of dip of the bed (measured from North in a clockwise direction). This will be a value between 0 and 360 degrees and can be typed in manually or populated using the slider to the right of the Azimuth text box. To move the slider small amounts click just to the left or just to the right of the slider's pointer and it will move 1 degree in that direction.

Tool Parameters

These three input values are parameters that affect how the tool calculates and displays structure contours. Each input is initially given a default value.

The three inputs are:


- 1. Tolerance:** At various points in the search area the tool calculates the predicted elevation of the bed and compares it with the ground elevation value from the DTM to see if they are the same. The tolerance value defines how close (in meters) these two values need to be to be declared 'the same'. This value can be typed in manually or populated using the slider to the right of the Tolerance text box. To move the slider small amounts click just to the left or just to the right of the slider's pointer and it will move 1 meter in that direction. A non-integer value (e.g. 0.5) can be entered as the tolerance, but this must be entered manually.
- 2. Sample Resolution:** For large search areas the time taken to produce structure contours can be high as calculations are made every 5 meters. To speed up the tool the distance between calculations can be increased. A sample resolution of 2 means calculations will be made every 10 meters, whilst a sample resolution of 3 means calculations will be made every 15 meters and so on. Increasing the sample resolution may decrease the number of points found that form structure contours. This value can be typed in manually or populated using the slider to the right of the Sample Resolution text box. To move the slider small amounts click just to the left or just to the right of the slider's pointer and it will move 1 in that direction.
- 3. Point Colour:** The colour used to display structure contours on the map display. Select from the pull down list of colours. Through the use of different colours it is possible to display the results of several structure contour calculations on the map display at the same time.

Search Area

These three input values are used to define a circular search area. Only structure contours that fall within this search area will be identified. The three inputs are:

- 1. Easting:** The National Grid Coordinate (Easting) of the centre of the search area. This value can be typed in manually or populated automatically as the Easting of the Observation Point by clicking on the Use Easting and Northing of Observation Point button.
- 2. Northing:** The National Grid Coordinate (Northing) of the centre of the search area. This value can be typed in manually or populated automatically as the Northing of the Observation Point by clicking on the Use Easting and Northing of Observation Point button.
- 3. Radius:** The radius in meters of the search area. This value can be typed in manually or a value can be selected from the dropdown list.

When all of the inputs have been entered, click on the Calculate button to run the tool. The progress of the tool is displayed, and once completed the results are displayed on the map display as graphics. An example result is shown below:



- The blue cross is the location of the Observation Point.
- The blue circle is the search area.
- Each red cross is a location where the estimated bed elevation is within the tolerance value of the ground elevation (forming a structure contour).

Important Notes on the use of the tool

The Structure Contours are drawn as graphics onto the map display of ArcMap. To make a permanent copy of the results they must be converted into a Shapefile. An additional tool is provided for this purpose and is described in section 4.2.1.3 below.


Slider controls have been included on the inputs form to simplify the process of manually entering values on a System. The easiest way to enter a precise value using the sliders is to drag the pointer of the slider to roughly the right value (within 1 or 2) and then click just to the left or just to the right of the slider's pointer (causing the value to increment or decrement by 1) until the precise value is displayed.

4.2.1.2 DELETE STRUCTURE CONTOURS

Clicking the Delete Structure Contours button will remove the graphics created by the Structure Contour tool from ArcMap's map display. Note that any other graphics on the map display (that were not created by the Structure Contour tool) will not be removed.

4.2.1.3 SAVE STRUCTURE CONTOURS AS SHAPEFILE

Clicking the save Structure Contours as Shapefile button allows the user to save all the points created by the Structure Contour tool to a Shapefile, which can then be retrieved at a later time. The user is presented with the following dialog:



Navigate to the required directory, enter a filename and then click on the Save button to complete the operation.

Note that it is possible to overwrite an existing Shapefile, but not if that Shapefile is currently being used in the active ArcMap project.

4.2.2 Limitations of the Structure Contour Tool



When choosing a DTM or multiple DTMs for the Structure Contour Tool, the user is able to select from all raster layers held in the GIS, as it is not possible to distinguish DTMs from other raster layers such as topography layers or photographs. Make sure that only DTMs are selected otherwise the Structure Contour Tool will attempt to get elevation values from a non-DTM raster layer.

5 Backing-up your data

We recommend that field data are backed-up each evening in the field in case your data becomes corrupted or the system fails. This also ensures that you will never lose more than one day of fieldwork.

Go to your Project area using Windows Explorer and Copy and Paste your DFDC.mdb file from your main Project Area to the ArchivedCopies Folder. Within the ArchivedCopies Folder rename DFDC.mdb to DFDC_UserID_Date, for example: DFDC_TEST_08092009.mdb

6 Viewing sketches on the Desktop

You can use the Précis Tool  in BGS-SIGMA*mobile* to view your sketches or you can use the edit  tool to edit a geological observation and also edit any associated sketch. The sketch tool on the System works with .ANT files in their native format, but it also saves a JPG file for use in any other programme.

7 Troubleshooting, bug reporting and feedback

Most bugs have been error trapped within the system either through the provision of a message box telling you what the problem is and how to alter it, or through internal code. However, it is possible that you may encounter errors. If you come across any, the developers would find it very valuable if you can document the error so that it can be fixed in a later release. Be patient with the system. There is a lot of code working in the background to reduce the amount of data entry and button clicking you have to do. This takes time to run, so occasionally you might find things don't work as quickly as you may like.


Some common errors include:

- **Not having the GeoPoly, GeoLine, National grid QS or Field observation point loaded into the GIS** or having them spelt incorrectly. These must be loaded, with the correct layer name spelling as in the blank BGS·SIGMA*mobile* GIS.
- If whilst using the BGS·SIGMA*mobile* system **you are asked to enable macros in Access2003** rather than viewing a data entry form, it is likely that you haven't set the security level to be low in Access. You will need to open the DFDC.mdb in Access 2003 and select Tools > Macro > Security and set the security level to low. This ensures that macros built in the system will work when fired up from ArcGIS.
- **The DFDC.mdb has been renamed**. This should never be renamed as the code between ArcMap and Access relies on knowing the access database filename.
- **If there is more than one version of the same .mxd open**, or there are two open MXD's pointing to the same geodatabase, this can cause problems with the code. Only use one .mxd project at a time.
- **If the user has changed a button image using the customize button**, this can upset the default path for editing and the editing tools will no longer work. If this happens, refresh the code in the VBA editor and go to File > Save As and overwrite the project. This resets the correct path.
- **If the database opens with an error**, check to ensure your virtual keyboard doesn't have SHIFT + CTRL highlighted. If this doesn't solve the problem, check to ensure that in Microsoft Access 2003 under Tools > Macro > Security, the security level is set to low.



8 Using BGS·SIGMA*mobile* outside the UK

When working outside the UK a different coordinate system to the British National Grid will be required. You will need to update BGS·SIGMA*mobile* (this includes the DFDC database and the ArcMap MXD project) to reflect the coordinate system you will be using. The following guidance notes describe how to do this. Please also remember to follow the generic BGS·SIGMA*mobile* installation instructions.


1. Copy a new empty BGS·SIGMA*mobile* project to your PC.
2. You need to replace the NationalGridQS layer, which is set up for the UK and references Ordnance Survey map sheets, with a layer that holds the map sheets for your country of working. BGS·SIGMA*mobile* uses a point in polygon operation to grab the NationalGridQS attribute value where you insert an observation point. The NationalGridQS polygon layer can therefore either be a real map sheet grid or could simply be a polygon covering the country in which you are working. It is essential that when creating the dataset using ArcCatalog you set the coordinate system to be that of your project.
3. With ArcMap closed, open ArcCatalog and within the DFDC rename the existing NationalGridQS to NationalGridQSBNG.
4. Create the new National Grid layer for the country you are mapping either by creating a new layer or importing a feature class or shapefile you already have. To import into the DFDC right-click on the DFDC.mdb and select import, feature_class (single). Browse to the feature class for the layer you are importing. Name the new layer as NationalGridQS.




5. It is essential that the new NationalGridQS layer you have created has a field name in its attribute table called QS. This should be a text field of maximum 50 characters and should be populated with the names of the map sheets.
6. Close ArcCatalog, open your BGS·SIGMA*mobile*.mxd ArcMap project and add the NationalGridQS layer. Open the attribute table and create a new field called QS. Add the sheet information into the QS field.
7. See the example below for a project created for mapping in Tanzania which shows the old NationalGridQSBNG layer with OS maps sheets and the new NationalGridQS showing Tanzanian map sheets.




- You need to set the coordinate system of the data frame to the coordinate system for your country of working. Open the Data Frame properties and select the Coordinate System tab. Select the appropriate coordinate system for your project or import one from a feature class that already has the coordinate system stored within it. Save the project and close ArcMap.
- Update the spatial references of some the feature classes in the DFDC database. In ArcCatalog browse to the project DFDC database. Add a new feature class called “TEST2” by selecting the DFDC.mdb and selecting File, New, Feature Class.




- In the New Feature Class dialogue, enter the name “TEST2”, and select point features as the type. Click Next.



11. Select the required coordinate system from the following window.



12. Select Next and continue clicking through the forms until clicking Finish.
13. The coordinate system for your country of mapping must also be added to the Field Observation Points, GeoLine, GeoPoly and Map Face Note data classes. Right click on each layer and click Properties. Select the XY Coordinate System tab and amend the Coordinate System as in 11 above. Close ArcCatalog.
14. In Windows Explorer, open the DFDC.mdb in Access 2003. If the database opens with only the Field Observation Entry Form viewable select Window, Unhide and click OK to view the database tables.
15. In the table view select the GDB_spatialRefs table and click Open or double click the table name.



16. One row in the table represents the spatial reference system for the “TEST2” data class you created. The SRTEXT field in this row should match the coordinate system you will be using. Select this row.

19	PROJCS[British_National_Grid,GEOGCS[GCS_OSGB_1936,DATU	-897468.1503	-387168.7453	976.56249909	0	100000	0	100000				
20	PROJCS[British_National_Grid,GEOGCS[GCS_OSGB_1936,DATU	70503.592176	903584.35018	999999.99907	0	100000	0	100000				
21	PROJCS[British_National_Grid,GEOGCS[GCS_OSGB_1936,DATU	-897468.1503	-387156.0823	976.56249909	0	100000	0	100000				
22	PROJCS[British_National_Grid,GEOGCS[GCS_OSGB_1936,DATU	70550.413176	903611.44168	999999.99907	0	100000	0	100000				
23	PROJCS[British_National_Grid,GEOGCS[GCS_OSGB_1936,DATU	-365990.7561	184353.71986	1953.124982	0	100000	0	100000				
24	PROJCS[British_National_Grid,GEOGCS[GCS_OSGB_1936,DATU	-5220399.999	-15524400	15624.999985	0	400000	0	100000				
25	GEOGCS[GCS_WGS_1984,DATUM[D_WGS_1984,SPHEROID[PW	-1070.571825	-1020.841825	999999.99907	0	400000	0	100000				
26	PROJCS[British_National_Grid,GEOGCS[GCS_OSGB_1936,DATU	-5220399.997	-15524400	11443.709862	1.#QNAN	1.#QNAN	1.#QNAN	1.#QNAN				
27	PROJCS[British_National_Grid,GEOGCS[GCS_OSGB_1936,DATU	-5220400	-15524400	15624.999985	0	400000	0	100000				
28	PROJCS[British_National_Grid,GEOGCS[GCS_OSGB_1936,DATU	-5220400	-15524400	999999.99907	0	400000	0	100000				
29	PROJCS[British_National_Grid,GEOGCS[GCS_OSGB_1936,DATU	-5220400	-15524400	16000	1.#QNAN	1.#QNAN	1.#QNAN	1.#QNAN				
30	PROJCS[British_National_Grid,GEOGCS[GCS_OSGB_1936,DATU	-5220400	-15524400	999999.99907	0	400000	0	100000				
31	PROJCS[British_National_Grid,GEOGCS[GCS_OSGB_1936,DATU	-5220400	-15524400	999999.99907	0	400000	0	100000				
32	PROJCS[British_National_Grid,GEOGCS[GCS_OSGB_1936,DATU	-5220400	-15524400	999999.99907	0	400000	0	100000				
33	PROJCS[British_National_Grid,GEOGCS[GCS_OSGB_1936,DATU	-5220399.999	-15524400	15624.999985	0	400000	0	100000				
34	PROJCS[British_National_Grid,GEOGCS[GCS_OSGB_1936,DATU	-5220400	-15524400	999999.99907	0	400000	0	100000				
35	PROJCS[British_National_Grid,GEOGCS[GCS_OSGB_1936,DATU	-5220399.999	-15524400	15624.999985	0	400000	0	100000				
36	PROJCS[British_National_Grid,GEOGCS[GCS_OSGB_1936,DATU	-5220400	-15524400	14198.238975	0	400000	0	100000				
37	PROJCS[British_National_Grid,GEOGCS[GCS_OSGB_1936,DATU	-5220400	-15524400	14198.238975	0	400000	0	100000				
38	GB360868-0979-11D3-AKA-000MA33320	-1073741.922	-1073741.922	4184304.0559	1.#QNAN	1.#QNAN	1.#QNAN	1.#QNAN				
39	PROJCS[WGS_1984_UTM_Zone_36S,GEOGCS[GCS_WGS_1984	-5120900	1900	10000	1.#QNAN	1.#QNAN	1.#QNAN	1.#QNAN				
40	PROJCS[WGS_1984_UTM_Zone_36S,GEOGCS[GCS_WGS_1984	-5120900	1900	10000	1.#QNAN	1.#QNAN	1.#QNAN	1.#QNAN				
41	PROJCS[WGS_1984_UTM_Zone_36S,GEOGCS[GCS_WGS_1984	-5120900	1900	10000	1.#QNAN	1.#QNAN	1.#QNAN	1.#QNAN				
42	PROJCS[WGS_1984_UTM_Zone_36S,GEOGCS[GCS_WGS_1984	-5220399.997	-15524400	11443.709862	1.#QNAN	1.#QNAN	1.#QNAN	1.#QNAN				

17. The rows after the selected row represent the Field Observation Points, Geotools (GeoLine and GeoPoly) and Map Face Note data classes and should all have the same coordinate system as the area you will be mapping, but the FalseX, FalseY, precision and XY Tolerance values will differ to your TEST2 dataset.


18. Replace the FalseX, FalseY, precision and XY Tolerance values in these four rows with the values found in your “TEST2” row.

39	PROJCS[WGS_1984_UTM_Zone_36S	-5120900	1900	10000	1.#QNAN	1.#QNAN	1.#QNAN	1.#QNAN	0.001
40	PROJCS[WGS_1984_UTM_Zone_36S	-5120900	1900	10000	1.#QNAN	1.#QNAN	1.#QNAN	1.#QNAN	0.001
41	PROJCS[WGS_1984_UTM_Zone_36S	-5120900	1900	10000	1.#QNAN	1.#QNAN	1.#QNAN	1.#QNAN	0.001
43	PROJCS[WGS_1984_UTM_Zone_36S	-5120900	1900	10000	1.#QNAN	1.#QNAN	1.#QNAN	1.#QNAN	0.001

19. Save changes, close the table and close the database.

20. Open your BGS-SIGMAmobile.mxd project. Try adding a field Observation point and add a sketch, Mapface note, GeoLine and GeoPoly within the QS map area of where you will be working. If you can do this, you have successfully modified BGS-SIGMAmobile to be used outside the UK. If not, check that you have completed the steps.

21. The final thing to do in order to have a working BGS-SIGMAmobile for your country of working is to change the hard coded reference system from BNG to the reference system you will be using. In the open BGS-SIGMAmobile.mxd go to Tools > Macros > Visual Basic Editor. Locate the module GW_FOP and double click on it to open the code. In the right hand window, scroll down to the “Public Sub AddFOP(obj As esriGeoDatabase.IObject)” code.



22. Within this sub there is some code that looks like the text shown below:

```

If pfield7 > -1 Then
    obj.value(pfield7) = "BNG"
End If


```

23. Change “BNG” to be the correct text to describe the coordinate system you are using. Note, you can only insert a word up to 6 characters long. Click Save and close down the visual basic editor.
24. You are now ready to populate the rest of the GIS with the data layers you require to take overseas. You will also have to ensure that the tablet is set up with the Structure Contour Tool and the BGS Sketch Tool. Please follow the generic installation instructions.

Appendix Using the Basic Précis Tool

Viewing the Précis of the observation point

If the user wishes to see basic text report of the notebook data (without thumbnails of photographs or sketches) for the given observation point they can create a précis by clicking the “View précis of FOP” button in the housekeeping section of the notebook.



The report will appear in a format similar to that shown below. To close the report, simply click on Close in the Précis Report Toolbar; clicking on the red X will close Access. The plan for future versions of BGS-SIGMAmobile is that the user will be able to hyperlink to these reports from with ArcMap. Until then, the user can manually export the précis using the file export button in Access and then set up their own hyperlink to the file in ArcMap.

